



INSTALLATION INSTRUCTIONS

Company setup

www.seavusprojectviewer.com

In order to install your Company License Key, you should check the notification and perform the following steps below:

Existing previous installation of Seavus Project Viewer™

If you have previous version of Seavus Project Viewer™ installed on client computers within your Company, before installing the latest version of the product you will have to uninstall the previous installations.

As an administrator you can remove the previous installation using the install/uninstall tool to remove the program from the previously installed computers. After uninstalling you will need to check if all the files/keys have been removed from the registry. To accomplish this please check if the following registry folders exist:

- "HKEY_LOCAL_MACHINE\SOFTWARE\Seavus\Seavus Project Viewer"- delete the "Seavus Project Viewer" folder if it exists.
- "HEKY_CURRENT_USER\ SOFTWARE\Seavus\Seavus Project Viewer" — delete the "Seavus Project Viewer" folder if it exists.
- In case you have used different License Key for the previous installation, go to "C:\Documents and Settings\All Users\Shared Documents\Seavus\Seavus Project Viewer" and delete the "Signature-txt" file.

Installing\deploying Seavus Project Viewer™ in your company

Once the previous installation has been removed or if this is your first installation, please follow the set of instructions below for the deployment of the Seavus Project Viewer™:

- Open your Seavus Project Viewer™ setup MSI file in an installation tool with the method and tool that you wish to use (Group Policy, SMS or Other tool). The MSI setup gives the administrators options to open the file in installation tool and creating additional MST (transform) file which can contain customizations that the administrator wishes to provide to the end users (ie. setting up the license key, the options to install shortcut on the desktop, etc).
- Create additional MST (transform) file, which contains customizations Of your choice (i.e. your License Key, shortcut on the desktop, quick launch, etc). There are many tools that can be used for creating the MST file.

Note: In case you don't have such tool, Seavus can assist you in creating this file. For that purpose you can send email to the following information:

- the language Of the application that you want to install o should the MPP files always be associated with Seavus Project Viewer™ o should there be a Seavus Project Vlewer™ desktop shortcut icon on the users PC's
- should there be a Seavus Project Viewer™ Quick Lunch icon
- should the application be installed on the default location (C:/Program Files/Seavus) or Other.

Publish the Seavus Project Viewer™ setup MSI file to the end-user computers synchronized with the MST (transform) file. Below you can see example of how you can synchronize them:

```
msiexec 'i "[path to setup folder]\SPV_FULL_CORP[version].msi" TRANSFORMS-"[path to MST folder]\SPV_FULL_CORP[version].mst
```

You can additionally add at the end of the line "/qb" for deployment with basic user interface or "/qn" for deployment without any user interface.

When the windows installer runs the setup transparently for the user, the MST file acts as if the user has run the setup themselves and chosen the options preselected by the administrator.

Installing Seavus Project Viewer™

Installation Instructions

After you have downloaded the setup, start the installation by double-clicking the setup file in Windows Explorer or use the "Run" command from the Start menu.

Note: Before you start the setup, you should check the section "System Requirements" in the "User Manual" document for information about the minimal hardware and software configuration required to run the product.

Note: You should have Administrator privileges during installation of the application.

STEP 1) SETUP INITIALIZATION

Once the setup is initialized and the initialization dialog appears; the Setup wizard will automatically continue with the installation.

Note: Click the Cancel button if you wish to exit the installation.


STEP 2) SETUP WELCOME

After the initial preparations for installation, the setup wizard will show you the Welcome dialogue. You should click the Next button if you want to continue with the Setup, or Cancel if you want to exit the wizard.



STEP 3) LICENSE AGREEMENT


The license agreement shows the End User License Agreement for the product. Please read it carefully, and click the "I accept the terms in the license agreement" radio button. Click the Next button if you agree with the License agreement and want to continue with the Setup, or click the Cancel button if you disagree with the License agreement and want to exit the installation wizard.



STEP 4) CUSTOMER INFORMATION

This dialog box collects the information about the user who performs the installation, and if the install is only for the current user or for all users of the PC. In this dialog the user enters his purchased License

Key information - the Serial Number. You must insert the correct serial number if you want to continue the Setup, otherwise you will not be allowed to install the product on your computer / server.



Seavus Project Viewer 15.1.0 Corporate Edition - InstallShield Wizard

Customer Information
Please enter your information.

User Name:

Organization:

Serial Number:
 - - - -

Install this application for:


☒ Anyone who uses this computer (all users)
☐ Only for me

InstallShield

< Back Next > Cancel

STEP 5) LANGUAGE DIALOG

This dialog box allows you to select which language Seavus Project Viewer™ will be installed on your PC. You may install Seavus Project Viewer™ in the following languages: English, German, French, Spanish, Czech, Russian, Chinese, Japanese, Dutch and Polish.



Seavus Project Viewer 15.1.0 Corporate Edition - InstallShield Wizard

Change Language Dialog

Choose the language that you want to install with the application.


English
English
German
French
Spanish
Czech
Japanese
Russian
Chinese
Dutch
Polish
Italian

InstallShield

< Back Next > Cancel


STEP 6) SETUP OPTIONS

For Trial version you can select which shortcuts should be placed for the application and whether you want to install the SharePoint integration or Skype for Business feature:




STEP 7) SETUP TYPE

Complete option will install it on the default location with all components.




Selecting the Custom type of installation gives you an opportunity to choose where the product will be installed and which components will be installed.




STEP 8) READY TO INSTALL THE PROGRAM

When you finish with all previous settings in the Setup screens, you are only a few steps from installing Seavus Project Viewer™ on your computer/server. If the settings are ok, you can click the Install button to start the installation.



STEP 9) INSTALLING THE PROGRAM

After you have clicked the Install button, the installation of the product will start. Once the installation dialog appears, you have the option to stop the installation by clicking the Cancel button. Cancelling the installation process will roll back the installation and remove all the data related to this product.



STEP 10) SETUP COMPLETED

If the installation was successful, the Installation Completed dialog box will appear informing you that the product is successfully installed on your computer/server. Click the Finish button, the complete the installation process.




Uninstalling Seavus Project Viewer™

There are several ways for uninstalling software from the PC. In the next steps, the most used routine for uninstalling application from PC will be described.

Note: Before you start the Seavus Project Viewer™ uninstallation process, you should consult with your IT personnel whether you are allowed to uninstall the software as well as the level of permissions that are assigned to your account.

STEP 1) CONTROL PANEL

For uninstalling Seavus Project Viewer™ you have to go to the Control Panel and in the Programs section select the “Uninstall a program” feature. Once this option is clicked, new window will appear presenting a list with all applications that are installed on your PC.




STEP 2) START UNSINTALL PROCESS

Scroll down and find the Seavus Project Viewer™ application. Select it and click on the “Uninstall” button, located at the top of the list.


STEP 3) CONFIRM UNINSTALLATION

Before starting the uninstall process, operating system will pop-up notification asking you whether you are sure with the intention to uninstall the software. Clicking on the Yes button will cause to continue the process. Otherwise, the installation process will be canceled.



STEP 4) USER ACCOUNT CONTROL

Uninstalling Seavus Project Viewer will cause changes your PC, and these changes will require administrator – level permission. The User Account Control (UAC) will notify you and gives you the chance to approve the uninstallation. After confirming the change that are going to be made on your PC, the uninstallation process will continue and end in few seconds.



Contact us:

customercenter@seavusprojectviewer.com

www.seavusprojectviewer.com